Package 'detectR'

March 8, 2024

Type Package

Title Change Point Detection

Version 0.3.0

Maintainer Changryong Baek <crbaek@skku.edu>

Description Time series analysis of network connectivity. Detects and visualizes change points between networks.

Methods included in the package are discussed in depth in Baek, C., Gates, K. M., Leinwand, B., Pipiras, V. (2021)

"Two sample tests for high-dimensional auto-covariances" <doi:10.1016/j.csda.2020.107067> and Baek, C., Gampe, M., Leinwand B., Lindquist K., Hopfinger J. and Gates K. (2023) "Detecting functional connectivity changes in fMRI data" <doi:10.1007/s11336-023-09908-7>.

License Unlimited

Encoding UTF-8

LazyData true

Imports signal, lavaan, doParallel, glasso, LogConcDEAD, foreach, parallel

Depends R (>= 2.10)

URL https://github.com/crbaek/detectR

RoxygenNote 7.3.1

NeedsCompilation no

Author Changryong Baek [aut, cre], Mattew Gampe [aut], Kathleen M. Gates [aut], Seok-Oh Jeong [aut], Vladas Pipiras [aut]

Repository CRAN

Date/Publication 2024-03-08 20:30:02 UTC

R topics documented:

changesim	2
detectBinary	2
detectGlasso	4
detectMaxChange	5
detectSliding	
global	7
preprocess	
testGlasso	
testMax	
testPCA	
testsim	11
	13

Index

changesim

Changepoint Example Data

Description

This dataset contains a simulated multivariate time series with two changepoints at time point 150 and 300. The dimension of the data is T=450 and p=20.

Usage

changesim

Format

An object of class matrix (inherits from array) with 450 rows and 20 columns.

detectBinary

Change point detection using PCA and binary segmentation

Description

This function uses PCA-based method to find breaks. Simultaneous breaks are found from binary segmentation.

detectBinary

Usage

```
detectBinary(
   Y,
   Del,
   L,
   q = "fixed",
   alpha = 0.05,
   nboot = 199,
   n.cl,
   bsize = "log",
   bootTF = TRUE,
   scaleTF = TRUE,
   diagTF = TRUE,
   plotTF = TRUE
)
```

Arguments

Υ	data: Y = length*dim
Del	Delta away from the boundary restriction
L	the number of factors
q	methods in calculating long-run variance of the test statistic. Default is "fixed" = $length^{(1/3)}$. Adaptive selection method is also available via "andrews", or user specify the length
alpha	significance level of the test
nboot	the number of bootstrap sample for p-value. Default is 199.
n.cl	number of cores in parallel computing. The default is (machine cores - 1)
bsize	block size for the Block Wild Bootstrapping. Default is log(length), "sqrt" uses sqrt(length), "adaptive" determines block size using data dependent selection of Andrews
bootTF	determine whether the threshold is calculated from bootstrap or asymptotic
scaleTF	scale the variance into 1
diagTF	include diagonal term of covariance matrix or not
plotTF	Draw plot to see test statistic and threshold

Value

tstathist The complete history of test statistics.

Brhist The sequence of breakpoints found from binary splitting

L The number of factors used in the procedure

q The estimated vectorized autocovariance on each regime.

crit The critical value to identify change point

bsize The block size of the bootstrap

diagTF If TRUE, the diagonal entry of covariance matrix is used in detecting connectivity changes. **bootTF** If TRUE, bootstrap is used to find critical value

scaleTF If TRUE, the multivariate signal is studentized to have zero mean and unit variance.

Examples

```
out3= detectBinary(changesim, L=2, n.cl=1)
```

detectGlasso	Change point detection using Graphical lasso as in Cribben et al.
	(2012)

Description

This function implements the Dynamic Connectivity Regression (DCR) algorithm proposed by Cribben el al. (2012) to locate changepoints.

Usage

```
detectGlasso(
    Y,
    Del,
    p,
    lambda = "bic",
    nboot = 100,
    n.cl,
    bound = c(0.001, 1),
    gridTF = FALSE,
    plotTF = TRUE
)
```

Y	Input data of dimension length*dim (T times d)
Del	Delta away from the boundary restriction
р	Gep(p) distribution controls the size of stationary bootstrap. The mean block length is 1/p
lambda	two selections possible for optimal parameter of lambda. "bic" finds lambda from bic criteria, or user can directly input the penalty value
nboot	the number of bootstrap sample for p-value. Default is 100.
n.cl	number of cores in parallel computing. The default is (machine cores - 1)
bound	bound of bic search in "bic" rule. Default is (.001, 1)
gridTF	minimum bic is found by grid search. Default is FALSE
plotTF	Draw plot to see test statistic

detectMaxChange

Value

A list with component

br The estimated breakpoints including boundary (0, T)
brhist The sequence of breakpoints found from binary splitting diffhist The history of BIC reduction on each step
W The estimated vectorized autocovariance on each regime.
WI The estimated vectorized precision matrix on each regime.
lambda The penalty parameter estimated on each regime.
pvalhist The empirical p-values on each binary splitting.
fitzero Detailed output at first stage. Useful in producing plot.

Examples

out1= detectGlasso(changesim, p=.2, n.cl=1)

```
detectMaxChange
```

Change point detection using max-type statistic as in Jeong et. al (2016)

Description

Change point detection using max-type statistic as in Jeong et. al (2016)

Usage

```
detectMaxChange(
    Y,
    m = c(30, 40, 50),
    margin = 30,
    thre.localfdr = 0.2,
    design.mat = NULL,
    plotTF = TRUE,
    n.cl
)
```

Y	Input data matrix
m	window sizes
margin	margin
thre.localfdr	threshold for local fdr
design.mat	design matrix for analyzing task data
plotTF	Draw plot to see test statistic and threshold
n.cl	number of clusters for parallel computing

Value

CLX Test statistic corresponding to window size arranged in column

CLXLocalFDR The Local FDR calculated for each time point

br The final estimated break points

Examples

out2= detectMaxChange(changesim, m=c(30, 35, 40, 45, 50), n.cl=1)

detectSliding Change point detection using PCA and sliding method

Description

Change point detection using PCA and sliding method

Usage

```
detectSliding(
 Y,
 wd = 40,
 L,
 Del,
 q = "fixed",
 alpha = 0.05,
 nboot = 199,
 n.cl,
 bsize = "log",
 bootTF = TRUE,
 scaleTF = TRUE,
 diagTF = TRUE,
 plotTF = TRUE
)
```

Y	data: $Y = length*dim$
wd	window size for sliding averages
L	the number of factors
Del	Delta away from the boundary restriction
q	methods in calculating long-run variance of the test statistic. Default is "fixed" = length $^{(1/3)}$ or "andrews" implements data adaptive selection, or user specify the length
alpha	significance level of the test

global

nboot	the number of bootstrap sample for p-value. Default is 199.
n.cl	number of cores in parallel computing. The default is (machine cores - 1)
bsize	block size for the Block Wild Bootstrapping. Default is log(length), "sqrt" uses sqrt(length), "adaptive" determines block size using data dependent selection of Andrews
bootTF	determine whether the threshold is calculated from bootstrap or asymptotic
scaleTF	scale the variance into 1
diagTF	include diagonal term of covariance matrix or not
plotTF	Draw plot to see test statistic and threshold

Value

sW The test statistic

L The number of factors used in the procedure

q The estimated vectorized autocovariance on each regime.

crit The critical value to identify change point

bsize The block size of the bootstrap

diagTF If TRUE, the diagonal entry of covariance matrix is used in detecting connectivity changes.

bootTF If TRUE, bootstrap is used to find critical value

scaleTF If TRUE, the multivariate signal is studentized to have zero mean and unit variance.

Examples

out4 = detectSliding(changesim, wd=40, L=2, n.cl=1)

global

Global Variables and functions

Description

Defining variables and functions used in the internal functions

preprocess

Data preparation for changepoint detection using functions in this package..

Description

Id

Usage

```
preprocess(file = NULL,
header = NULL,
sep = NULL,
signal = NULL,
noise = NULL,
butterfreq = NULL,
model = NULL)
```

file	a data matrix or file name with columns as variables and rows as observations across time.
header	logical for whether or not there is a header in the data file.
sep	The spacing of the data files. "" indicates space-delimited, "/t" indicates tab- delimited, "," indicates comma delimited. Only necessary to specify if reading data in from physical directory.
signal	(optional) a character vector containing the names of variables that contain sig- nal i.e., which variables to use to detect change point. The default (NULL) indicates all variables except those in 'noise' argument are considered signal. Example: signal = c("dDMN4", "vDMN5", "vDMN1",
noise	(optional) a character vector containing the names of variables that contain noise. The signal variables will be regressed on these variables and residuals used in change point detection. The default (NULL) indicates there are no noise variables. Example: noise = $c("White.Matter1", "CSF1")$
butterfreq	(optional) bandpass filter frequency ranges. Example: c(.04,.4)
model	(optional) syntax indicating which variables belong to which networks for first pass of data reduction that is user-specified. If no header naming convention follows "V#". Notation should follow lavaan syntax style.

testGlasso

Description

This function utilizes Dynamic Connectivity Regression (DCR) algorithm proposed by Cribben el al. (2012) to test the equality of connectivity in two fMRI signals.

Usage

```
testGlasso(
    subY1,
    subY2,
    p,
    lambda = "bic",
    nboot = 100,
    n.cl,
    bound = c(0.001, 1),
    gridTF = FALSE
)
```

Arguments

subY1	a sample of size length*dim
subY2	a sample of size length*dim
р	Gep(p) distribution controls the size of stationary bootstrap. The mean block length is 1/p
lambda	two selections possible for optimal parameter of lambda. "bic" finds lambda from bic criteria, or user can directly input the penalty value.
nboot	the number of bootstrap sample for p-value. Default is 100.
n.cl	number of cores in parallel computing. The default is (machine cores - 1)
bound	bound of bic search in "bic" rule. Default is (.001, 1)
gridTF	Utilize a grid search to optimize hyperparameters

Value

pval The empirical p-value for testing the equality of connectivity structure

rho The sequence of penalty parameter based on the combined sample, subY1 and subY2.

fit0 Output of glasso for combined sample

fit1 Output of glasso for subY1

fit2 Output of glasso for subY2

Examples

test1= testGlasso(testsim\$X, testsim\$Y, n.cl=1)

testMax

Description

This function produces three test results based on max-type block bootstrap (BMB), long-run variance block bootstrapping with lagged-window estimator (LVBWR) and sum-type block bootstrap (BSUM). See Baek el al. (2019) for details.

Usage

```
testMax(subY1, subY2, diagTF = TRUE, nboot, q = "fixed", n.cl)
```

Arguments

subY1	a sample of size length*dim
subY2	a sample of size length*dim
diagTF	include diagonal term of covariance matrix or not
nboot	number of bootstrap sample, default is 2000
q	methods in calculating long-run variance of the test statistic. Default is "fixed" = $length^{(1/3)}$ or "andrews" implements data adaptive selection, or user specify the length
n.cl	number of cores in parallel computing. The default is (machine cores - 1)

Value

tstat Test statistic for testing the equality of connectivity structure

pval The p-value for testing the equality of connectivity structure

q The tuning parameter used in calculating long-run variance

Examples

test2 = testMax(testsim\$X, testsim\$Y, n.cl=1)

testPCA

Description

This function performs PCA-test for testing the equality of connectivity in two fMRI signals

Usage

testPCA(subY1, subY2, L = 2, nlag, diagTF = TRUE)

Arguments

subY1	a sample of size length*dim
subY2	a sample of size length*dim
L	the number of factors
nlag	is the number of ACF lag to be used in the test, default is 2, Default is nlag = $floor(N^{(1/3)})$
diagTF	include diagonal term of covariance matrix or not

Value

tstat Test statistic

pval Returns the p-value

df The degree of freedom in PCA-best test

L The number of factors used in the test

diagTF If true, the diagonal entry of covariance matrix is used in testing

Examples

test3 = testPCA(testsim\$X, testsim\$Y, L=2)

testsim

Test Example Data

Description

This dataset contains a simulated multivariate time series with two different autocovariances. It is a list data with two variables X and Y. Each multivariate time series had dimension of T=150 and p=20

Usage

testsim

testsim

Format

An object of class list of length 2.

Index

* datasets changesim, 2 testsim, 11 changesim, 2 detectBinary, 2 detectGlasso, 4 detectMaxChange, 5 detectSliding, 6 global, 7 preprocess, 8 testGlasso, 9

testMax, 10 testPCA, 11 testsim, 11